



Where ministry clicks™

Where ministry clicks™

Design reference information Greater Pure Light Church (81219) 4/1/2008

This document gives you specifics about your custom design features as of the indicated date. Changes made to the design after that date may not be reflected in this information.

Links are included to reference articles in our Knowledge Base, available on your Extranet when you log in at www.myelexio.com. To use the following links, you will need to log in to the Extranet.

The design is located at <http://site81219.web05.intellisite.com/>

Your design information:

- Image slide show: The images should be sized to 494 pixels wide x 240 pixels high. See: [Changing the Images in a Slide show Area](#) and [Making a Flash header image link to a page](#)
- Channels: You have three channels on your home page. These currently contain simple headings and standard Latin design filler text, but you can edit and configure each channel as desired. See: [Updating Channels](#)
- Header links (at the top of your page): To edit the links displayed in this area, in your Pages module go to the Header Links folder. You can add, remove, or rename pages in this folder to control the function of these links.
- Sub page design options:
 - Your default sub page has just a content area without the Flash image
 - Your "Wide Page" design option that does not include the side menu, giving you the full width for your page content.
- Page-specific audio player
You control the audio that plays on your site by placing your song files (mp3 format) into specific folders in your files area.
 - In your site Control Panel, go to the Files module
 - In the Files area, note the folder named "mp3". This is the folder that contains the songs that will play on your site. Here is how they are controlled:
 1. "Default" – mp3 files in this folder will play on your home page.
 2. "SubPage Default" – mp3 files in this folder will play on your sub pages.
 3. Creating other folders – to have different audio playing on a specific page of your web site, create a folder within "mp3" with the same name as that specific page, and place the desired mp3 files in that folder.

For example, to set up different songs playing on a page titled “Youth Ministry”, go to the Files module, open the “mp3” folder, and create a folder titled “Youth Ministry”, then place the desired mp3 files in that “Youth Ministry” folder.

- The page specific function also works for any of the folders in your Pages module. If you wanted to have a certain song playing on all of the pages with in the “Youth” Page folder of your site, then you can accomplish that by going to the “mp3” folder in your Files area and creating a “Youth” folder within “mp3”. Any mp3 files you place in the “Files/mp3/Youth” folder will play on pages within the “Youth” section of the site.

These design options are applied to pages as desired by going to the Pages module, selecting the page, and going to the “Design” selection box above the Edit button. Once you select the desired option, click “Save” to complete the change.

Your home page content area is below the image slide show, and can be edited as you would edit a standard page.

If you have any questions about working with your custom design, please open a support request.

Thank you!